


Memory management


UNIT III

- **MEMORY MANAGEMENT:** Memory hierarchy – Linking and Loading the process – Memory Management requirement - Fixed partitioning - Dynamic partitioning – Buddy Systems – Simple paging – Simple Segmentation – segmentation and paging.

Memory Hierarchy




Memory linking and loading the process



Base and Limit Registers

- A pair of **base** and **limit** registers define the logical address space

- CPU must generate between



memory access
be sure it is
that user


Address Binding

- **Programs on disk, ready to be brought into memory to execute form an input queue**
 - ◆ Without support, must be loaded into address 0000
- **Inconvenient to have first user process physical address always at 0000**
 - ◆ How can it not be?
- **Further, addresses represented in different ways at different stages of a program's life**
 - ◆ Source code addresses usually symbolic
 - ◆ Compiled code addresses **bind** to relocatable addresses
 - ☞ i.e. "14 bytes from beginning of this module"
 - ◆ Linker or loader will bind relocatable addresses to absolute addresses
 - ☞ i.e. 74014
 - ◆ Each binding maps one address space to another

Binding of Instructions and Data to Memory

- **Address binding of instructions and data to memory addresses can happen at three different stages**
 - ◆ **Compile time:** If memory location known a priori, **absolute code** can be generated; must recompile code if starting location changes
 - ◆ **Load time:** Must generate **relocatable code** if memory location is not known at compile time
 - ◆ **Execution time:** Binding delayed until run time if the process can be moved during its execution from one memory

Multistep Processing of a User Program



Logical vs. Physical Address Space

- **The concept of a logical address space that is bound to a separate physical address space is central to proper memory management**
 - ◆ **Logical address** – generated by the CPU; also referred to as **virtual address**
 - ◆ **Physical address** – address seen by the memory unit
- **Logical and physical addresses are the same in compile-time and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding**


Memory Management

- **Is the task carried out by the OS and hardware to accommodate multiple processes in main memory**
- **If only a few processes can be kept in main memory, then much of the time all processes will be waiting for I/O and the CPU will be idle**
- **Hence, memory needs to be allocated efficiently in order to pack as many processes into memory as possible**

Memory Management

- **In most schemes, the kernel occupies some fixed portion of main memory and the rest is shared by multiple processes**

Memory Management Requirement



Memory Management Requirements

■ Relocation

- ◆ programmer cannot know where the program will be placed in memory when it is executed
- ◆ a process may be (often) **relocated** in main memory due to swapping
- ◆ swapping enables the OS to have a larger pool of ready-to-execute processes
- ◆ memory references in code (for both instructions and data) must be translated to actual physical memory address

Memory Management Requirements

■ Protection

- ◆ processes should not be able to reference memory locations in another process without permission
- ◆ impossible to check addresses at compile time in programs since the program could be relocated
- ◆ address references must be checked at run time by hardware

Memory Management Requirements

■ Sharing

- ◆ must allow several processes to access a common portion of main memory without compromising protection
 - ☞ cooperating processes may need to share access to the same data structure
 - ☞ better to allow each process to access the same copy of the program rather than have their own separate copy

Memory Management Requirements

■ Logical Organization

- ◆ users write programs in modules with different characteristics
 - ☞ instruction modules are execute-only
 - ☞ data modules are either read-only or read/write
 - ☞ some modules are private others are public
- ◆ To effectively deal with user programs, the OS and hardware should support a basic form of module to provide the required protection and sharing

Memory Management Requirements

■ Physical Organization


- ◆ secondary memory is the long term store for programs and data while main memory holds program and data currently in use
- ◆ moving information between these two levels of memory is a major concern of memory management (OS)
 - ☞ it is highly inefficient to leave this responsibility to the application programmer

Simple Memory Management


- In this chapter we study the simpler case where there is **no virtual memory**
- An executing process must be loaded entirely in main memory (if overlays are not used)
- Although the following simple memory management techniques are not used in modern OS, they lay the ground for a proper discussion of virtual memory (next chapter)
 - ◆ fixed partitioning
 - ◆ dynamic partitioning
 - ◆ simple paging
 - ◆ simple segmentation

Fixed Partitioning

- Partition main memory into a set of non overlapping regions called **partitions**
- Partitions can be of equal or unequal sizes



Equal-size partitions



Unequal-size partitions

Fixed Partitioning

- any process whose size is less than or equal to a partition size can be loaded into the partition
- if all partitions are occupied, the operating system can swap a process out of a partition
- a program may be too large to fit in a partition. The programmer must then design the program with overlays
 - ◆ when the module needed is not present the user program must load that module into the program's partition, overlaying whatever program or data are there

Fixed Partitioning

- Main memory use is inefficient. Any program, no matter how small, occupies an entire partition. This is called **internal fragmentation**.
- Unequal-size partitions lessens these problems but they still remain...
- Equal-size partitions was used in early IBM's OS/MFT (Multiprogramming with a Fixed number of Tasks)


Placement Algorithm with Partitions

- **Equal-size partitions**

- ◆ If there is an available partition, a process can be loaded into that partition
 - ☞ because all partitions are of equal size, it does not matter which partition is used
- ◆ If all partitions are occupied by blocked processes, choose one process to swap out to make room for the new process


Placement Algorithm with Partitions

- **Unequal-size partitions: use of multiple queues**
 - ◆ assign each process to the smallest partition within which it will fit
 - ◆ A queue for each partition size
 - ◆ tries to minimize internal fragmentation
 - ◆ Problem: some queues will be empty if no processes within a size range is present



Placement Algorithm with Partitions


- **Unequal-size partitions: use of a single queue**
 - ◆ When its time to load a process into main memory the smallest available partition that will hold the process is selected
 - ◆ increases the level of multiprogramming at the expense of internal fragmentation



Dynamic Partitioning


- Partitions are of variable length and number
- Each process is allocated exactly as much memory as it requires
- Eventually holes are formed in main memory. This is called **external fragmentation**
- Must use **compaction** to shift processes so they are contiguous and all free memory is in one block
- Used in IBM's OS/MVT (Multiprogramming with a Variable number of Tasks)

Dynamic Partitioning: an example



- A hole of 64K is left after loading 3 processes: not enough room for another process
- Eventually each process is blocked. The OS swaps out process 2 to bring in process 4


Dynamic Partitioning: an example



- another hole of 96K is created
- Eventually each process is blocked. The OS swaps out process 1 to bring in again process 2 and another hole of 96K is created...
- Compaction would produce a single hole of 256K

Placement Algorithm

- Used to decide which free block to allocate to a process
- Goal: to reduce usage of compaction (time consuming)
- Possible algorithms:
 - ◆ **Best-fit**: choose smallest hole
 - ◆ **First-fit**: choose first hole from beginning
 - ◆ **Next-fit**: choose first hole from last placement



Example Memory Configuration Before and After Allocation of 16 Kbyte Block

Placement Algorithm: comments

- **Next-fit often leads to allocation of the largest block at the end of memory**
- **First-fit favors allocation near the beginning: tends to create less fragmentation than Next-fit**
- **Best-fit searches for smallest block: the fragment left behind is small as possible**
 - ◆ main memory quickly forms holes too small to hold any process: compaction generally needs to be done more often

Replacement Algorithm

- **When all processes in main memory are blocked, the OS must choose which process to replace**
 - ◆ A process must be swapped out (to a Blocked-Suspend state) and be replaced by a new process or a process from the Ready-Suspend queue
 - ◆ We will discuss later such algorithms for memory management schemes using virtual memory

Buddy System

- A reasonable compromise to overcome disadvantages of both fixed and variable partitioning schemes
- A modified form is used in Unix SVR4 for kernel memory allocation
- Memory blocks are available in size of $2^{\{K\}}$ where $L \leq K \leq U$ and where
 - ◆ $2^{\{L\}}$ = smallest size of block allocatable
 - ◆ $2^{\{U\}}$ = largest size of block allocatable (generally, the entire memory available)

Buddy System

- We start with the entire block of size $2^{\{U\}}$

 Das Bild kann zurzeit nicht angezeigt werden.

- When a request of size S is made:
 - ◆ If $2^{\{U-1\}} < S \leq 2^{\{U\}}$ then allocate the entire block of size $2^{\{U\}}$
 - ◆ Else, split this block into two buddies, each of size $2^{\{U-1\}}$
 - ◆ If $2^{\{U-2\}} < S \leq 2^{\{U-1\}}$ then allocate one of the 2 buddies
 - ◆ Otherwise one of the 2 buddies is split again
- This process is repeated until the smallest block greater or equal to S is generated
- Two buddies are coalesced whenever both of them become unallocated

Buddy System

- **The OS maintains several lists of holes**
 - ◆ the i -list is the list of holes of size $2^{\{i\}}$
 - ◆ whenever a pair of buddies in the i -list occur, they are removed from that list and coalesced into a single hole in the $(i+1)$ -list
- **Presented with a request for an allocation of size k such that $2^{\{i-1\}} < k \leq 2^{\{i\}}$:**
 - ◆ the i -list is first examined
 - ◆ if the i -list is empty, the $(i+1)$ -list is then examined...

Example of Buddy System

1 Mbyte block	1 M					
Request 100 K	A = 128 K	128 K	256 K	512 K		
Request 240 K	A = 128 K	128 K	B = 256 K	512 K		
Request 64 K	A = 128 K	C = 64 K	64 K	B = 256 K	512 K	
Request 256 K	A = 128 K	C = 64 K	64 K	B = 256 K	D = 256 K	256 K
Release B	A = 128 K	C = 64 K	64 K	256 K	D = 256 K	256 K
Release A	128 K	C = 64 K	64 K	256 K	D = 256 K	256 K
Request 75 K	E = 128 K	C = 64 K	64 K	256 K	D = 256 K	256 K
Release C	E = 128 K	128 K	256 K	D = 256 K	256 K	
Release E	512 K			D = 256 K	256 K	
Release D	1 M					

Relocation

- Because of swapping and compaction, a process may occupy different main memory locations during its lifetime
- Hence physical memory references by a process cannot be fixed
- This problem is solved by distinguishing between **logical address** and **physical address**

Address Types

- A **physical address** (absolute address) is a physical location in main memory
- A **logical address** is a reference to a memory location independent of the physical structure/organization of memory
- Compilers produce code in which all memory references are logical addresses
- A **relative address** is an example of logical address in which the address is expressed as a location relative to some known point in the program (ex: the beginning)

Address Translation

- **Relative address is the most frequent type of logical address used in pgm modules (ie: executable files)**
- **Such modules are loaded in main memory with all memory references in relative form**
- **Physical addresses are calculated “on the fly” as the instructions are executed**
- **For adequate performance, the translation from relative to physical address must be done by hardware**

Simple Paging

- Main memory is partitioned into equal fixed-sized chunks (of relatively small size)
- Trick: each process is also divided into chunks of the same size called **pages**
- The process pages can thus be assigned to the available chunks in main memory called **frames** (or page frames)
- Consequence: a process does not need to occupy a contiguous portion of memory

Example of process loading

Frame number	Main memory
0	
1	
2	
3	
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	

(a) Fifteen Available Pages

Frame number	Main memory
0	A.0
1	A.1
2	A.2
3	A.3
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	

(b) Load Process A

Frame number	Main memory
0	A.0
1	A.1
2	A.2
3	A.3
4	B.0
5	B.1
6	B.2
7	
8	
9	
10	
11	
12	
13	
14	

(b) Load Process B

Frame number	Main memory
0	A.0
1	A.1
2	A.2
3	A.3
4	B.0
5	B.1
6	B.2
7	C.0
8	C.1
9	C.2
10	C.3
11	
12	
13	
14	

(d) Load Process C

- Now suppose that process B is swapped out

Example of process loading (cont.)

- When process A and C are blocked, the pager loads a new process D consisting of 5 pages
- Process D does not occupied a contiguous portion of memory
- There is no external fragmentation
- Internal fragmentation consist only of the last page of each process

	Main memory
0	A.0
1	A.1
2	A.2
3	A.3
4	
5	
6	
7	C.0
8	C.1
9	C.2
10	C.3
11	
12	
13	
14	

(e) Swap out B

	Main memory
0	A.0
1	A.1
2	A.2
3	A.3
4	D.0
5	D.1
6	D.2
7	C.0
8	C.1
9	C.2
10	C.3
11	D.3
12	D.4
13	
14	

(f) Load Process D

Page Tables

0	0
1	1
2	2
3	3

Process A
page table

0	—
1	—
2	—

Process B
page table

0	7
1	8
2	9
3	10

Process C
page table

0	4
1	5
2	6
3	11
4	12


Process D
page table

13
14

Free frame
list

- The OS now needs to maintain (in main memory) a **page table** for each process
- Each entry of a page table consist of the frame number where the corresponding page is physically located
- The page table is indexed by the page number to obtain the frame number
- A free frame list, available for pages, is maintained

Paging Example



$n=2$ and $m=4$ 32-byte memory and 4-byte pages

Paging (Cont.)

- **Calculating internal fragmentation**

- ◆ Page size = 2,048 bytes
- ◆ Process size = 72,766 bytes
- ◆ 35 pages + 1,086 bytes
- ◆ Internal fragmentation of $2,048 - 1,086 = 962$ bytes
- ◆ Worst case fragmentation = 1 frame – 1 byte
- ◆ On average fragmentation = 1 / 2 frame size
- ◆ So small frame sizes desirable?
- ◆ But each page table entry takes memory to track
- ◆ Page sizes growing over time
 - ☞ Solaris supports two page sizes – 8 KB and 4 MB

Logical address used in paging


- Within each program, each logical address must consist of a **page number** and an **offset** within the page
- A CPU register always holds the starting physical address of the page table of the currently running process
- Presented with the logical address (page number, offset) the processor accesses the page table to obtain the physical address (frame number, offset)

Logical address in paging

- The logical address becomes a relative address when the page size is a power of 2
- Ex: if 16 bits addresses are used and page size = 1K, we need 10 bits for offset and have 6 bits available for page number
- Then the 16 bit address obtained with the 10 least significant bit as offset and 6 most significant bit as page number is a location relative to the beginning of the process

Logical address =
Page# = 1, Offset = 478


0000010111011110



Logical address in paging

- **By using a page size of a power of 2, the pages are invisible to the programmer, compiler/assembler, and the linker**
- **Address translation at run-time is then easy to implement in hardware**
 - ◆ logical address (n,m) gets translated to physical address (k,m) by indexing the page table and appending the same offset m to the frame number k

Logical-to-Physical Address Translation in Paging



Simple Segmentation

- Each program is subdivided into blocks of non-equal size called **segments**
- When a process gets loaded into main memory, its different segments can be located anywhere
- Each segment is fully packed with instructs/data: no internal fragmentation
- There is external fragmentation; it is reduced when using small segments


Simple Segmentation

- **In contrast with paging, segmentation is visible to the programmer**
 - ◆ provided as a convenience to organize logically programs (ex: data in one segment, code in another segment)
 - ◆ must be aware of segment size limit
- **The OS maintains a **segment table** for each process. Each entry contains:**
 - ◆ the starting physical addresses of that segment.
 - ◆ the length of that segment (for protection)

Logical address used in segmentation

- When a process enters the Running state, a CPU register gets loaded with the starting address of the process's segment table.
- Presented with a **logical address (segment number, offset) = (n,m)**, the CPU indexes (with n) the segment table to obtain the starting physical address k and the length l of that segment
- The physical address is obtained by **adding** m to k (in contrast with paging)
 - ◆ the hardware also compares the offset m with the length l of that segment to determine if the address is valid


Logical-to-Physical Address Translation in segmentation



Simple segmentation and paging comparison


- Segmentation requires more complicated hardware for address translation
- Segmentation suffers from external fragmentation
- Paging only yield a small internal fragmentation
- Segmentation is visible to the programmer whereas paging is transparent
- Segmentation can be viewed as commodity offered to the programmer to organize logically a program into segments and using different kinds of protection (ex: execute-only for code but read-write for data)
 - ◆ for this we need to use protection bits in segment table entries

Free Frames



(a)

Before allocation



(b)

After allocation

References

- Silberschatz A, Galvin P B and Gagne G, “Operating System Concepts Essentials”, John Wiley & Sons, New York, 2011.
- William Stallings, “Operating Systems”, Pearson Education, New Delhi, 2009
- H.M Deitel., “Operating Systems”, 2nd Edition, Pearson Education Publ., 2003
- Achyut S Godbole, “Operating Systems”, TMH Publ., 2002.
- <https://www.geeksforgeeks.org/difference-between-loading-and-linking/>